VPN HOWTO WINDOWS 8-10 ver 2.1

Copyright by CC/IESL-FORTH

Set up the PPTP VPN on Windows 8-10

This step-by-step tutorial shows how to setup a PPTP connection on Windows and start using VPN servers.

Step 1.Open Network and Sharing Center from Control Panel. Then choose Set up a new connection or network.



🍸 Set U	p a Connection or Network	
Choose	a connection option	
-	Connect to the Internet Set up a broadband or dial-up connection to the Internet.	
2	Set up a new network Set up a new router or access point.	
	Connect to a workplace Set up a dial-up or VPN connection to your workplace.	

Step 2. In the next window, choose: Connect to a workplace and click Next.

Step 3. In the next window, choose Use my Internet Connection (VPN).



Step 4. Under Internet address type vpn.iesl.forth.gr

Step 5. Then enter **IESL-FORTH VPN** as the name of the connection in the **Destination name** box (you can name it as you want). Then click **Create**.

←	🌆 Connect to a Workplace				\sim	
	Type the Internet add	ress to connect to				
	Your network administrator	can give you this address.				
	Internet address:	vpn.iesl.forth.gr				
	Destination name:	IESL-FORTH VPN				
	 Use a smart card Remember my credentials Allow other people to use this connection This option allows anyone with access to this computer to use this connection. 					
		Cr	reate	Cano	el	

Step 6. Click on the network icon on the bottom right-hand corner.

Step 7. Click again on the network monitor icon on the bottom right-hand corner, find **IESL-FORTH VPN** connection and click **connect**.

朢	Network 2 Connected
જ	IESL-FORTH VPN
Netw	vork settings
	🐝 📨 🐔 🖞 📴 🔛 ላ») 😻 틎 ENG



Step 8. Type your email address (<u>username@iesl.forth.gr</u>) and password and click OK.

Sign in					
Sign in					
8					
User name					
Password					
Domain:					
		ок	Cancel		
· ← Settings				-	\times
 Settings NETWORK & INTERNET 			Find a setting	-	× م
 Settings NETWORK & INTERNET Data usage 	VPN		Find a setting	-	× م
 Settings NETWORK & INTERNET Data usage VPN 	VPN		Find a setting	_	× م
 Settings NETWORK & INTERNET Data usage VPN Dial-up 	VPN + Add a VPN connection		Find a setting	-	× م
 Settings NETWORK & INTERNET Data usage VPN Dial-up Ethernet 	VPN + Add a VPN connection VPN connected		Find a setting	-	× م
 Settings NETWORK & INTERNET Data usage VPN Dial-up Ethernet Proxy 	VPN + Add a VPN connection VESL-FORTH VPN Connected Add	dvanced options	Find a setting	-	× م
Settings Image Data usage VPN Dial-up Ethernet Proxy	VPN + Add a VPN connection Connected VPN Advanced Setti	dvanced options	Find a setting Disconnect	-	× م
 Settings NETWORK & INTERNET Data usage VPN Dial-up Ethernet Proxy 	VPN + Add a VPN connection (IESL-FORTH VPN Connected Add VPN Advanced Setti Allow VPN connections over Me On	dvanced options NGS etered networks	Find a setting	-	× Q

Done, your Windows now should be connected to the VPN server.